



**DSTAR**

**Manual**

# **Index**


- 1. Input Trajectory**
- 2. Target Dataframe**
- 3. Generate Fingerprint and Train ML Model**
  - 3 – 1. Only Generation or Training**
  - 3 – 2. Other Arguments**
- 4. Fingerprint Substitution**
  - 4 – 1. Elements & Substitution Type Selection**
  - 4 – 2. Other Arguments**
- 5. Target Prediction from Substituted Fingerprint**

# 1. Making Input Trajectory

1) Save surfaces with tagged adsorbates as trajectory file format to `~/DSTAR/atoms/` for training

```
/home/ahrehd0506/git/DSTAR/atoms
(base) [ahrehd0506@haber atoms]$ ls
0.traj  11.traj 13.traj 15.traj 17.traj 19.traj 20.traj 2.traj  4.traj  6.traj  8.traj
10.traj 12.traj 14.traj 16.traj 18.traj 1.traj  21.traj 3.traj  5.traj  7.traj  9.traj
```

※ **Adsorption atoms** should be tagged with **non-zero integer**, and **the other surface atoms** are tagged with **zero**.



## 2. Making Target Dataframe

1) Generate Dataframe with **name** and **target** columns. It doesn't matter if there are other columns

2) **name** column indicates **name (id) of input surface trajectory file** and **target** column indicates **corresponding target value** (In our study, binding energy)

surface named 12.traj with target value 4

	name	target
0	1	1
1	2	2
2	3	3
3	4	4
4	5	5
5	6	6
6	7	7
7	8	8
8	9	9
9	0	1
10	10	2
11	11	3
12	12	4
13	13	5
14	14	6
15	15	7
16	16	8
17	17	9
18	18	1
19	19	2
20	20	3
21	21	4

3) Save filled Dataframe named **target.csv** to **~/DSTAR/atoms/**

```
(base) [ahrehd0506@haber atoms]$ pwd
/home/ahrehd0506/git/DSTAR/atoms
(base) [ahrehd0506@haber atoms]$ ls
0.traj  11.traj 13.traj 15.traj 17.traj 19.traj 20.traj 2.traj  4.traj  6.traj  8.traj  target.csv
10.traj 12.traj 14.traj 16.traj 18.traj 1.traj  21.traj 3.traj  5.traj  7.traj  9.traj
```



4) Fingerprint file named **fp.csv** will be generated in **~/DSTAR/data/**. It contains surface informations converted into active motif-based fingerprint.

1	name	FNN	Same	Sub	target	
2		0 {'Co': 1, 'Si': 1}	{'Co': 5, 'Si': 3}	{'Al': 2}		1

surface named 0.traj converted into the number of elements in FNN / SNN\_same / SNN\_sub site

※ Can change file name and path by running with **--data-path {your\_data\_path}** argument (Default : **./data/fp.csv**)

```
python main.py --data-path /data/test.csv
```

5) **ML model** and **Scaler** used in training will be saved as **~/DSTAR/model/{current-date}/model.pkl & scaler.pkl**

```
(base) [ahrehd0506@haber model]$ ls
2022-06-01/ 2022-06-02/ 2022-06-03/ 2022-07-13/
(base) [ahrehd0506@haber model]$ cd 2022-07-13/
(base) [ahrehd0506@haber 2022-07-13]$ ls
model.pkl  scaler.pkl
```

## 3 – 1. Only Generation or Training

1) Only **generate fingerprint** by running with **--convert-only** argument (Default : **False**)

```
(base) [ahrehd0506@haber DSTAR]$ python train.py --convert-only
Namespace(algo='total', atom_path='./atoms/', convert_only=True,
th='./subs/fp/', test=False, test_ratio=0.2)

Initiate Conversion Atoms to Fingerprint...
100%|
Successfully Generate Fingerprint!
```

2) Only **train model** from existed fingerprint by running with **--load-data --data-path {your\_data\_path}** argument  
(data-path Default : **./data/fp.csv**)

```
(base) [ahrehd0506@haber DSTAR]$ python train.py --load-data --data-path ./data/test.csv
Namespace(algo='total', atom_path='./atoms/', convert_only=False, data_path='./data/test.
path='./subs/fp/', test=False, test_ratio=0.2)

Load Motif From test.csv...
Initiate Conversion Motifs to Fingerprint...
22it [00:00, 148.06it/s]
Successfully Generate Fingerprint!

2022-07-13 13:44:51,304 - INFO - Start Gradient Boosting Regression
2022-07-13 13:44:53,923 - INFO - Start Kernel Ridge Regression
2022-07-13 13:44:53,943 - INFO - Start ElasticNet Regression
```



## 3 – 2. Other Arguments

1) Change input trajectory files path for training by running with `--atom-path {your_atom_path}` argument (Default : [./atoms/](#))

2) Adjust the train / test ratio by running with `--test-ratio {test_ratio}` argument (Default : 0.2)

3) Change ML algorithm by running with `--algo {algorithm}` argument (Default : Use all and choose the best)

Available Algorithms : GBR / KRR / ELN / SVR / GRP



## 4. Fingerprint Substitution

1) Substitute elements in the fingerprint file generated from previous process

2) Run `python subs.py` in `~/DSTAR/`. Successful if displayed as below image

```
(base) [ahrehd0506@haber DSTAR]$ python subs.py
Namespace(bi_only=False, data_path='./data/fp.csv', get_bi=False, subs_path='./subs/fp/', subs_type='comb')

Initiate Active Motif Substitution
100%|
Successfully Generate New Active Motifs!!
```

※ Can change fingerprint file for substitution by running with `--data-path {your_data_path}` argument (Default : `./data/fp.csv`)

3) Substituted fingerprints files will be saved in `~/DSTAR/subs/{your_subs_path}/` (Default : `~/DSTAR/subs/fp/` )

```
(base) [ahrehd0506@haber fp]$ ls
Ag_Ag.csv  Al_Al.csv  As_Au.csv  Au_Cu.csv  Co_In.csv  Cr_Os.csv  Cu_Ru.csv  Fe_W.csv  Ge_Os.csv
Ag_Al.csv  Al_As.csv  As_Co.csv  Au_Fe.csv  Co_Ir.csv  Cr_Pb.csv  Cu_Sb.csv  Fe_Zn.csv  Ge_Pb.csv
```

## 4 – 1. Elements & Substitution Type Selection

1) Can change elements for substitution by modifying **el\_set\_A** / **el\_set\_B** list in Line 31~34 from [~/DSTAR/sub.py](#)

```
def subs(args):
```

```
    el_set_A = ['Ag', 'Al', 'As', 'Au', 'Co', 'Cr', 'Cu', 'Fe', 'Ga', 'Ge', 'In', 'Ir', 'Mn', 'Mo',  
               'Ni', 'Os', 'Pb', 'Pd', 'Pt', 'Re', 'Rh', 'Ru', 'Sb', 'Se', 'Si', 'Sn', 'Ti', 'V',  
               'W', 'Zn']  
    el_set_B = []
```

default elements in el\_set\_A (30 Transition Metals)  
role of el\_set\_B is described below

2) Select substitution type by running with **--subs-type {subs\_type}** argument (Default : comb)

- **comb** : Combination N elements in **el\_set\_A** ( ${}_N P_2$ )
- **prod** : Product between **el\_set\_A** and **el\_set\_B**
- **ex**) If you want substitute with combination between Metal + Chalcogen, modify like below image and use **prod**

```
el_set_A = ['Ag', 'Al', 'As', 'Au', 'Co', 'Cr', 'Cu', 'Fe', 'Ga', 'Ge', 'In', 'Ir', 'Mn', 'Mo',  
            'Ni', 'Os', 'Pb', 'Pd', 'Pt', 'Re', 'Rh', 'Ru', 'Sb', 'Se', 'Si', 'Sn', 'Ti', 'V',  
            'W', 'Zn']  
el_set_B = ['O', 'S', 'Se', 'Te']
```

## 4 – 2. Other Arguments

1) Change substituted fingerprint save path by running with `--subs-path {your_subs_path}` argument (Default : `./subs/fp/`)

2) Substitute without unary materials ( $_N C_2$ ) by running with `--bi-only` argument (Default : **False**)

3) Extract original fingerprint only with binary materials by running with `--get-bi` argument (Default : **False**)

(Automatically substitute only binary without this arg.)

Extracted fingerprint only with binary materials saved as `{your_data_path}/{data_name}_binary.csv` (Default : `./data/fp_binary.csv`)

## 5. Target Prediction from Substituted Fingerprint

1) Run `python train.py --test --model-path {your_model_path}` in `~/DSTAR/`.  
Successful if displayed as below image.

```
(base) [ahrehd0506@haber DSTAR]$ python train.py --test --model-path ./model/2022-07-13/  
Namespace(algo='total', atom_path='./atoms/', convert_only=False, data_path='./data/fp.cs  
3/', subs_path='./subs/fp/', test=True, test_ratio=0.2)  
  
Load Model 2022-07-13  
Initiate Screening...  
100%|  
Successfully Predict Ideal Surface Density!!
```

※ **model path argument must be included**

※ Can change substituted fingerprint files path by running with  
`--subs-path {your_subs_path}` argument (Default : `./subs/fp/`)

2) **pred** column (predicted target value will be added in fingerprint files in  
`{your_subs_path}`)

	name	FNN	Same	Sub	target	pred
0		5 {'Ag': 1}	{'Ag': 2}	{'Ag': 1}	0	4
1		5 {'Ag': 1}	{'Ag': 2}	{'Ag': 1}	0	4



There are two same ids because both  
 $A_xB_y / B_xA_y$  are substituted from one material

4) dens.csv file will be generated in `~/DSTAR/`, which contains **elements** and **density** column.

**desnity** indicates the ratio of surfaces with predicted target value within **desire target range**. → higher, the better activity.

※ Set desire target for ideal surface by running with `--desire-target {target_value}` argument  
(Default :  $-0.67$  , Ideal CO binding energy for CO2RR)

※ Set target error range for ideal surface by running with `--desire-range {range_value}` argument  
(Default :  $\pm 0.1$ )

A	D
elements	density
Ga_Ge	0
Fe_Pd	0
As_Ru	0
Re_Zn	0
Fe_Ti	0
Fe_Se	0
Ga_Pb	0
Fe_Fe	0
Au_Re	0
Cr_Mn	0
Ag_Ga	0